

# Install SeligSim 2026 on Linux

First you will need to have wine installed. On my debian system this can be done with the command

```
$ sudo apt install wine
```

For non-debian base systems (fedora, arch, etc) please consult your system documentation

Download the iso image for SeligSim. Usually this will go in your `~/Downloads` directory. Lets verify that it is there.

```
$ ls -l ~/Downloads/Selig*  
-rw-rw-r-- 1 gwen gwen 2296709120 Sep 17 16:01  
/home/gwen/Downloads/SeligSIM_2026a-20-1_Full_Installer.iso
```

Now we need to get inside the file. If you don't have directory called `/media/cdrom` lets create one

```
$ mkdir /media/cdrom
```

Next we are going to mount that file so its contents show up in `/media/cdrom`

```
$ sudo mount ~/Downloads/SeligSIM_2026a-20-1_Full_Installer.iso  
/media/cdrom2 -o loop
```

Then make sure everything looks ok

```
$ ls /media/cdrom  
SeligSIM_2026a-20-1_Full_Installer-1a.bin  
SeligSIM_2026a-20-1_Full_Installer-1b.bin  
SeligSIM_2026a-20-1_Full_Installer.exe
```

Looking good! Now we can install.

```
$ wine /media/cdrom/SeligSIM_2026a-20-1_Full_Installer.exe
```

At this point the install window should pop up and you can follow the instructions there. If it doesn't pop up hit Control-C in the terminal window to get the prompt back and try:

```
$ WINEDEBUG=warn+all wine /media/cdrom/SeligSIM_2026a-20-1_Full_Installer.exe
```

If that still doesn't work, please ask for help on the [RCGroups.com](https://www.rcgroups.com/forums/) simulator forum (there should be a thread there for SeligSim on linux) and include the last page or two of the debugging statements. I had some issues with the installer starting but it worked fine on a clean reboot

Once the install is done you should be able to start it with.

```
$ cd .wine/drive_c/SeligSIM\ 2026/  
$ wine SeligSIM.exe
```

Accessing SeligSim from the Gnome menus worked after logging out and logging back in

I highly recommend that once you have your transmitter plugged in, start SeligSim and use the Mapping feature to configure your controller. Once you do that the default setting for the airplanes should mostly work straight out of the box.